

## Changelog - Protein Firmware 1.01



### New Features:

#### **Filter**

- New 12 dB Low-Pass & High-Pass modes

#### **Presets**

- Increased preset storage from 250 to 360

#### **Limit Waves option in Wavetable to avoid the last 3 generic waveforms**

In the osc screen press the "Table" or "Display" encoder to get to new details screen.

Press the encoder to change between "All Waves" and "Limit Waves" mode.

Turn and press encoder to choose "Close" in order to leave details screen.

Setting is made individually per osc.

#### **Glide Mode**

In the Glide screen choose between "Onset" and "Legato" glide mode with the display encoder.

The pitch bend range has been moved to new pitch details screen.

#### **Pitch Details Screen**

While in Pitch screen (Semitone or Detune) press the "Semitone" or "Display" encoder to show the details screen.

Turn the encoder to change the pitch bend range. Press the encoder and choose "Close" to leave the details screen.

### Bug Fixes and Improvements:

- Do not jump to edit screen anymore after loading presets but stay in Preset screen.
- Improved Pot relative mode: Keep relative value change with direction of knob movement.
- Further improved Pot relative mode for certain parameters like "Wave" and "Drive Type".